




심플리파이 3D 설치 및 사용

- 리덤 카드 보유 시

기본 사용 안내

- 사용자 1명당 한 계정을 생성함으로써 해당 계정에서 아이디/이메일 변경, 제품 다운로드, 설치 컴퓨터 관리 등을 진행할 수 있음
- 라이선스 1개 당 컴퓨터 2대에 동시 설치가 가능하며, 프로그램 삭제가 아닌 프로그램 비활성화를 통해 컴퓨터 간 라이선스 이동이 가능함 (라이선스 이동 방법은 STEP15 참조)

Step1



- 제품 박스 내 동봉되어 있는 Simplify3D 책자에서 회색 스크래치를 지워 30자리 코드 확인

Step2

Your Name (required)

Email (required)

Email Confirmation

Redemption Code (required)

Redeem Code!

- www.simplify3d.com/redeem 접속
- 위부터 차례로 이름(한글 가능), 메일 주소(2회 입력), 카드의 코드 입력 후 Redeem Code 클릭

Step3

From: no-reply@simplify3d.com

Subject: Your Simplify3D Software Purchase

Date:

To:

SIMPLIFY3D®

Your Simplify3D Software Purchase

Order #

Thank you for purchasing a license to the Simplify3D Software!

As part of your purchase, we have automatically created a Simplify3D account for you. This account will be your gateway for accessing and using the software.

Please click the link below to verify your account and to begin downloading the Simplify3D Software.

[Verify Account](#)

- 입력한 메일 주소로 발송된 Simplify3D Purchase 메일 확인(미발송 시 스팸함 확인)
- 하단의 녹색 Verify Account 클릭하여 계정 생성

Step4

Finalize Your Simplify3D Account

Welcome to your new Simplify3D Account! Please create a username and password for this account so that you can access it in the future.

You will use this same username and password combination when installing the desktop software.

Username

Password

Confirm Password

Finalize Account

- 계정 로그인 시 사용하고자 하는 ID(Username)와 Password(2회 입력)를 입력
- 입력 후 Finalize Account를 클릭. 이 때 패스워드는 8글자 이상으로 입력해야 함

Step5

SIMPLIFY3D® HOME SOFTWARE BUY NOW SUPPORT BLOG COMMUNITY ACCOUNT

ACCOUNT You are here: Home - Account

Previous Simplify3D User? - Start Here.

The new Version 3.0 software upgrade from Simplify3D contains dozens of new features, including a brand new user account system. This account allows you to manage your license details and gain access to the latest Simplify3D content such as future software releases and updated printer profiles.

Previous Simplify3D users can upgrade their accounts using the link below. You will need to enter your license information, so please have that ready.

Upgrade Now to Download Version 3.0

Already Upgraded? - Login to Your Account

Username

Password

Remember Me

Login [Forgot Password?](#)

- <https://simplify3d.com/account> 접속 후 화면 오른쪽에 ID/PW 입력 후 Login 클릭

Step6



jslee

Dashboard

Account Settings

Download

Devices

Logout

Download Options

This page allows you to download the installer for the Simplify3D desktop software. After installing the software, you will be asked for your username and password so that the software can be linked to your Simplify3D account.

Operating System



Windows 64-bit

Download Software Installer

Windows Installation Instructions


- Unzip the .zip file and double-click the .exe file to install.
- **Note:** You may need to right-click and choose "Run as administrator" depending on your security settings.

- 이후 계정 화면 왼쪽 메뉴에서 Download 클릭, 윈도우 버전 선택 후 다운로드 클릭





- 설치파일 다운 후 실행, 동의 체크 후 진행. 설치 완료 후 ID/PW 입력

Step7





- 위 화면이 나타나면 화면 상의 Cancel을 눌러 프로그램 실행

Step8




- File >> Import FFF profile을 클릭한 후
메일에 첨부된 최신 버전의 설정 파일
(FFF형식) 불러오기

Step9




- 화면 왼쪽 하단의 Add 클릭 후 나타나는 창에서 Select Profile 선택하여 불러와진 Moment 설정 값을 선택, OK 클릭

Step10




- ① 소재 선택 – PLA/ABS/Flexible/Wood, 기타 소재 문의 요망
- ② 출력 퀄리티(한 레이어 두께) 선택(Fast-0.3mm / Medium-0.2mm / High-0.1mm)
- ③ 내부 채우기 설정 – 기본 추천 값 20%(5~100% 선택 가능)
- ④ 지지대(서포트) 생성 체크 – 체크 시 지지대가 필요한 부분을 자동 인식하여 출력
(기본 체크 추천)

Step11




- 왼쪽 상단 Import 클릭하여 슬라이싱 할 stl 파일을 불러올 수 있음
- 왼쪽 하단 창에서 Process1 을 더블 클릭하여 설정 값을 확인·수정 할 수 있음

Step12




- 불러온 모델링 파일을 더블 클릭하여 크기, 각도, 위치 등을 조정할 수 있음
- 수동 서포트 생성 시 오른쪽 메뉴 중 Customize Support Structures 클릭

Step 13




- 설정 완료 후 왼쪽 하단의 Prepare to Print! 버튼 클릭하여 슬라이싱 변환

Step 14



- 변환 완료 후 왼쪽 하단의 Save toolpaths to Disk 클릭하여 SD카드 저장
- USB 프린팅의 경우, 모멘트 홈페이지 > Support > 모멘트 매뉴얼 중 13p 참조

Step15



- 사용 중인 컴퓨터에서 라이선스를 비활성화하고 다른 컴퓨터에서 활성화할 때, 메인 메뉴 중 Help >> Deactivate Product를 클릭하여 Yes 클릭
- 이후 새로운 컴퓨터에서 STEP6 부터 반복하여 재 설치
- * 한 번 설치된 컴퓨터에서는 프로그램을 삭제하지 않고 최초 로그인만을 통해서 라이선스 재등록 가능

계정 관리



haloveher

Dashboard

Account Settings

Download

Devices

Logout

Linked Devices

This page allows you to see which devices have been successfully linked to your Simplify3D account. If you ever need to move your license to a new device, you can do that by uninstalling the software from the old computer and selecting "Yes" when asked if you would like to remove your license from that machine.

In extreme circumstances such as a hard drive failure or a stolen computer, the "Reset Device" button can be used to forcefully unlink a specific device. **Only use this option in extreme circumstances!**

Device 1

Install Date: 2015-05-19 20:45:08

Operating System: Windows

Reset Device

Device 2

Install Date: 2015-06-18 22:43:45

Operating System: Windows

Reset Device

- www.simplify3d.com/account에 접속, 로그인하여 사용중인 계정을 관리
- Account 로그인 후 Devices 를 클릭하면 현재 설치된 기기 정보를 확인할 수 있음
- Reset Device: 프로그램 비활성화를 하지 않고 프로그램을 삭제하거나 컴퓨터를 포맷했을 때, 해당 버튼을 클릭해 등록된 컴퓨터 정보를 초기화할 수 있음
- Account Settings 에서는 사용자 정보 입력, Email 주소 및 PW 변경을 할 수 있음